



CC26X2 Series

OTA Quick Start User Guide

Version: 1.0

Shenzhen RF-star Technology Co., Ltd.

August 12th, 2022


Table of Contents

Table of Contents.....	2
1 OTA Preparation.....	3
2 OTA Process.....	5
3 Revision History.....	9
4 Contact Us.....	10



1 OTA Preparation



A. Install the official OTA APP. Find the iOS version in the APP store.



Andriod version is as follows, you can ask RF-star to supply the APK.



B. Obtain the OTA file (.bin file) required for the upgrade.


 BLE5_TTM_CC26X2_115200_20220208.bin	2022/1/21 15:06	BIN 文件	154 KB
 BLE5_TTM_CC26X2_115200_20220208.hex	2022/2/8 9:22	HEX 文件	366 KB

Save the .bin file in a familiar path on your phone, so that you can easily find it and use the OTA file to upgrade.




2 OTA Process


A. Open the OTA APP and find the devices that need to be upgraded.




B. The interface after connecting is shown as follows, press “TEST TARGET” button to wait for the sting of “Device disconnected!”.




C. After the device is disconnected, refind the broadcasting device with the name of “OAD Persistent APP” and click connect.




D. After reconnection, click "TIOAR Service" and the interface is as follows:



E. Click "SELECT CUSTOM FW" to choose the OTA file that needs to be updated.



F. After successfully choosed, the OTA is starting. Wait for the "Success".



3 Revision History

Date	Version No.	Description
2022.08.12	V1.0	The initial version is released.

Note:

1. The document will be optimized and updated from time to time. Before using this document, please make sure it is the latest version.
2. To obtain the latest document, please download it from the official website: www.rfstariot.com and www.szrfstar.com.



4 Contact Us

SHENZHEN RF-STAR TECHNOLOGY CO., LTD.

Shenzhen HQ:

Add.: C601, Skyworth Building, High-tech Park, Nanshan District, Shenzhen, Guangdong, China, 518057

Tel.: 86-755-3695 3756

Chengdu Branch:

Add.: N2-1604, Global Center, North No. 1700, Tianfu Avenue, Hi-Tech District, Chengdu, Sichuan, China, 610095

Tel.: 86-28-6577 5970

Email: sunny@szrfstar.com, sales@szrfstar.com

Web.: www.rfstariot.com, www.szrfstar.com

